PSFC User Manual

Table of Contents

Introduc	tion
Develop	ment
Citation	
License.	
	started
	ation
	al use case
1.	Load the network
2.	Load node input data
3.	
	Load edge types attribute
4.	Define flow propagation rules
5.	Define loop handling options
6.	Significance calculation options
7.	Flow calculation
8.	Signal flow visualization
9.	Final output of PSFC
Gettir	ng started example: the MAPK signaling pathway
1.	Load the network
2.	Load node and edge attributes.
3.	Set signal propagation rules
4.	Set loop handling options
5.	Calculate flow
6.	PSFC output1

7. Visualize the flow	14
GUI components	
Network tab	15
Rules tab	17
Network sorting	
Flow rule configurations	
Pathway flow calculation	
Flow visualization	

Introduction

The Pathway Signal Flow Calculator (PSFC) is a Cytoscape app for calculation of pathway signal flow based on input data and pathway topology. The app provides a flexible interface for setting flow propagation rules and applying algorithms of wide range to assess activity states of pathway nodes (PSF values). The app supports visualization of signal propagation on the network.

Development

The app has been developed by Lilit Nersisyan and Arsen Arakelyan, from the Bioinformatics Group at the Institute of Molecular Biology of the National Academy of Sciences of the Republic of Armenia (IMB NAS RA) in collaboration with Graham Johnson, and Megan Riel-Mehan from University of California, and Alexander Pico from Gladstone Institutes.

The project was funded by Google Summer of Code 2014, and Armenian National Science and Educational Foundation Grant research grant molbio-3818 (PI: LN).

Citation

When using the app in your research, please link the app's webpage at http://apps.cytoscape.org/apps/psfc and the paper at http://f1000research.com/articles/tba as:

TBA

License

Copyright © 2015
Lilit Nersisyan, IMB NAS RA
Arsen Arakelyan, IMB NAS RA
Graham Johnson, UCSF
Megan Riel-Mehan, UCSF
Alexander Pico, UCSF

This program is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License version 3. The license can be found at http://www.gnu.org/licenses/gpl.html.

Getting started

Installation

In Cytoscape, go to Apps -> "App Manager", choose PSFC under and click on the install button. In case of successful installation, the "PSFC" app tab should appear in the west panel of Cytoscape (Figure 1).




Figure 1. Installation of PSFC.

General use case




Figure 2. The general use case of PSFC.

1. Load the network

PSFC works on any pathway network loaded into Cytoscape environment. The network may either be loaded with File -> Import -> Network from a local file, or from the web, with available pathway parser apps, such as WikiPathways, CyKEGGParser, KEGGScape, ReactomeFIPlugin, etc.

2. Load node input data

The nature of node data may vary: it can be absolute or relative expression of genes in each node, fold change of expression values, node ranks, protein concentration, protein phosphorylation level, etc. Basically, this is any data related to the activity states or the quantities of the nodes. The node data should be loaded in Cytoscape node attribute table. This can be done manually in Cytoscape Table Panel, via File -> Import -> Table from a local file.

3. Load edge types attribute

The edge types actually define how the signal is propagated between nodes in the network. The type of the edge should be loaded in Cytoscape edge attribute table. As explained below, each edge type may be associated with a different mathematical function.

4. Define flow propagation rules

After step 2-3, each node is assigned a value, and each edge is described with a specific behavior. Flow propagation rules define: (i) how the signal is passed from a source node to a target node via an edge; and (ii) how nodes receiving multiple signals from multiple source nodes process those signals, and vice-versa. These rules are defined upon the user's choice.

5. Define loop handling options

Biological pathways contain positive and negative feedback loops. In PSFC provides a number of options for handling loops in pathways.

6. Significance calculation options

The output of signal flow calculation is PSF values assigned to each node that describes the activity state of the node. The significance of the PSF values is calculated with Bootstrap resampling. The user may choose to compute significance values, and may select different options for resamplings.

7. Flow calculation

After setting the configurations, PSF computation is performed with a click of the "Compute flow" button. PSFC outputs PSF values for all the nodes and edges in the pathway. These values describe the amount of signal that a node carries and an edge transfers.

8. Signal flow visualization

The signal propagation may be visualized on the network via node color mapping and edge width mapping, according to node and edge signal values.

9. Final output of PSFC

The PSF values of nodes and signals at edges are mapped to Cytoscape node and edge attribute tables, and are also written in a backup file.

The following columns appear in the Node attribute table:

psfc.level.

This column appears after network sorting. The level of each node is equal to the distance of that node to the pathway input. The input nodes have level 0, the sink nodes have the highest levels in their branch.

psf_I(x)

These columns are used for signal flow visualization, and may be of little interest to the user.

The signal flow propagation is performed from 0 level nodes to higher level nodes. After a level x is processed, a column psf_lx appears, where the node PSF (signal) values are kept. For example, in psf_l2, only 0, 1 and 2 levels are processed, and the PSF (signal) values of nodes of those levels are updated, while the rest of the nodes have PSF values equal to their original input values. Note that when performing many iterations, only values of the last iteration are displayed.

psf_final

This column contains the final PSF values of all the nodes, when all the levels are processed. In case of many iterations of PSF calculations, the PSF values of the last iteration are displayed.

psfc_pval

The significance p values of the PSF values for each node.

The following columns appear in the Edge attribute table:

psfc_isbackward

This column appears after network sorting. If true, then the edge is a loop forming backward.

psfc_l(x)

These columns are used for signal flow visualization, and may be of little interest to the user. The signal flow propagation is performed from 0 level nodes to higher level nodes. After a level x is processed, a column psf_lx appears, where the edge signals in the current state are kept. For example, in psf_l2, only 0, 1 and 2 levels are processed, and the signals of the edges of those levels are updated, while the rest of the edges have signals equal to 1. Note that when performing many iterations, only values of the last iteration are displayed.

Getting started example: the MAPK signaling pathway


This is a quick demonstration the app workflow. The MAPK signaling pathway structure is taken from previous publications:

- 1. Nelander S, Wang W, Nilsson B, *et al*: Models from experiments: combinatorial drug perturbations of cancer cells. *Mol Syst Biol.* 2008; **4**: 216.
- 2. Feiglin A, Hacohen A, Sarusi A, *et al*: Static network structure can be used to model the phenotypic effects of perturbations in regulatory networks. *Bioinformatics*. 2012; **28**(21): 2811-8.


For following the demo, go to http://big.sci.am/apps/psfc/MAPK_psfc_configurations.rar, and download the model network and configuration files.

1. Load the network

Go to File -> Import -> Network -> File, and navigate to "MAPK_model.xml" directory, click Open to load the network into Cytoscape.




Press on the refresh buttons in the PSFC "General" tab, to notify it about the newly loaded network and attributes. From the **Network** dropdown menu choose the MAPK network.



2. Load node and edge attributes.

The MAPK network contains two types of edges: activation and inhibition. In the following steps, each of these edge types will be assigned a different mathematical function for signal transfer. The edge type attribute is loaded in the Cytoscape edge attribute table, in the **type** column. In PSFC **General** tab, select the **type** column from



Control Panel 52_mapk_model_1 Network Style Select PSFC General Options Rules Loops Help Network and attributes 52_mapk_model_1:SUID52 🔻 🔾 Edge type attribute ▼ Check type Node data attribute SUID shared name name selected p-S6 isExcludedFromPaths Label Show state Table Panel Play flow **♦** □ **88** 00 □ f(x)p-MEK
EGFR
p-RAF
p-eIF4E MEK MEK p-MEK EGFR p-RAF p-eIF4E 52_mapk_model_1:SUID52 PSFC log p-eIF4E false Calculate flow Save settings Node Table | Edge Table | Network Table

the **Edge type attribute** drop-down menu.

The node data is in the node attribute table, under the column **fc.** The values in this column represent fold changes of protein phosphorylation levels in a studied condition compared to the control.


In our network, all the nodes have initial values of 1.0 that correspond to the control (not changed) state.

Furthermore, we will change the values of different nodes of the pathway, to see how these changes propagate to other nodes and to the sink nodes of the pathway. From the **Node data attribute** drop-down menu in the PSFC **General** tab, choose the **fc** column.

3. Set signal propagation rules

Simple rules

In biological pathway representations, an edge is a connector between a source and a target node, which transfers the signal from the source to the target. Edges may have different functional annotations. In our network, there are edges of type activation that increase the activity of the target node, and those of type inhibition, that decrease it. We would like to simulate these functional annotations of edges by defining a function for each of those. For this we will go the **Rules** tab **Simple rules** panel. There are two configuration files: the **Edge types config file** is a tab separated file, where each edge type is assigned a function name. The mathematical functions corresponding to each of these function names are defined in the **Rule config file**. Those are in the form *f*(*source*, *target*), where *source* and *target* variables are source signal and target value respectively.



Multiple input and output edge rules

Following these simple rules for single edges, we should also define how the signal should be transferred if a single source node has multiple outgoing edges, or many edges are incoming to the same target node.


These rules are set with the **Multiple input and output edge rules** panel in the **Rules** tab. For details on various rules in the panel, refer to further sections of the manual. We will now discuss the rules set for the MAPK signaling pathway.

- signal on is set to Incoming. This means that the signal coming from multiple edges to the same target node, will be split or assigned weights, based on relative values of their source nodes. Biologically, this simulates the fact that when interacting with multiple competing partners, the interaction intensity of the molecule depends on relative concentrations/activity states of those partners.
- The Multiple signal processing rule is set to Addition. With this rule, the signals from multiple edges coming to the same target node will be added to each other, and the sum will be the signal transferred to the target edge.




4. Set loop handling options

Biological pathways contain positive and negative feedback loops, which are important regulators of pathway activity and properties. The MAPK signaling pathway contains many negative feedback loops. Those can be seen by applying the Topological sorting algorithm by clicking the **Sort** button in the **Options** tab, and checking the **Change network layout after sorting** checkbox.



The backward edges introduce cycles in the graph, complicate signal flow propagation on the pathway. Among the three choices for loop handling presented in the **Loops** tab, we will choose the **until convergence option**, with parameters: Convergence threshold **Maximum number of iterations** = 50. This means that the flow propagation will be performed on the whole pathway for multiple times, updating the signal flow on the nodes after each iteration, until reaching convergence. A convergence is achieved, if the relative signal change between two consecutive iterations is less than 1% for all the nodes in the pathway. If convergence is not achieved, the algorithm will stop after **50** iterations.




5. Calculate flow

Now that the rules are set, we can calculate the flow on the pathway. Before that, recall that all the nodes had **fc** values of 1. This means that all the nodes have the same value as the control state, thus no signal will be propagated in the network (you may check this by calculating the flow). Thus, we will change the **fc** value


of the IGF1R node to 0.1, down-regulating it, and will calculate the signal propagation resulting from this perturbation.

The flow is calculated by clicking the **Calculate flow** button at the bottom of the **PSFC** panel.

Note that a number of columns will appear in the node and edge attribute tables, that describe the PSF values of nodes and edges during signal propagation on the network: from lower levels (input nodes) to




higher levels (sink nodes). There is a column named **psf_final**, which keeps the final output of PSFC.



6. PSFC output


Besides the signal values in the node and edge attribute tables, PSFC tracks a log file, where the input, the option and the results of the computation are stored. The log file may be accessed by clicking the **PSFC log** button at the bottom of the **PSFC** panel. According to the results of our calculations, convergence was reached at iteration 7.



Additionally, the sorting-level-wise PSF values of the nodes after the last iteration are stored in an .xls file, with the name of the network. The file is located in the Cytoscape directory, usually in the c:\Users\User\CytoscapeConfiguration\app-data\PSFC\ path.


7. Visualize the flow

The flow propagation on the last iteration is visualized based on level-wise the PSF values of nodes. The signal is visualized from lower levels of the pathway to the highest ones. Note that the layout of the pathway does not correspond to the sorted order, as shown in step 4. To see how the signal flow propagates through the network, click on the **Play flow** button in the **General** tab.



GUI components

General tab




Contains the following components:

- 1. *Network* combo-box: for selection of the network under interest. The networks are represented in the form *networkName*:SUID*networkSUID*. If the chosen network is in the current view the network label (15) is green, otherwise it is red. Note that there is no listener on the network view change: one should push the refresh button (2) for the label color to change accordingly.
- 2. Refresh button for *Network* combo box updates the list of currently loaded networks. Should be used after a new network has been loaded or removed.
- 3. Select Edge type attribute combo box for selecting the Edge type attribute from the selected network's Default Edge Table. The Edge type attribute is used for defining the types of edges in the network and further setting edge type specific rules (see Flow rule configurations section).
- 4. Refresh button for *Select Edge type attribute* combo box updates the list of columns of the selected network's Default Edge Table. Should be used when a column is added or removed from the table.

- 5. Check button for Select Edge type attribute combo box shows the list of unique values in the selected Edge type column. The list is just for checking all the unique types of edges in the network, as well as for copying those for the rule configuration file (see Flow rule configurations section).
- 6. Select Node data attribute combo box for selecting the Node data attribute from selected network's Default Node Table. The Node data attribute is used for setting the initial values of nodes for flow calculation. Node data values can be either row of logarithmic expression values, fold change or log-fold change of expression values, etc.
- 7. Refresh button for *Select Node data attribute* combo box updates the list of columns of the selected network's Default Node Table. Should be used when a column is added or removed from the table.
- 8. Flow visualization panel for performing visual mapping of node and edge signals after SPF calculation.
- 9. Level textbox and slider for setting the PSF state at the specified level in the sorted network. A level of the sorted network specifies the distance of nodes from the pathway input. The signal is propagated from the 0 level to the highest level in the pathway (see Network sorting for details).
- 10. *Show state* button performs color gradient visual mapping based on the node signals, and edge width mapping based on the edge signals, at the chosen level.
- 11. *Play flow* button performs color gradient visual mapping based on the node signals, and edge width mapping based on the edge signals, for all the levels in sequence.
- 12. Calculate flow button Performs PSF calculation on the selected network.
- 13. *PSFC log* button Open the PSFC log file in the default text browser. If the file is not opening, open it manually, from the path indicated in the Cytoscape Task Manager.
- 14. Save settings button saves the options from all the tabs.

Options tab




Contains the following components:

- 1. Sorting algorithm combo box for selection of the sorting algorithm to be applied on the network. Currently only a modified version of topological sort algorithm is supported (see PSFC algorithms for details). In short, sorting assigns each node a level, which indicates the distance of that node from the nearest input node. The signal flow is propagated from the input nodes that have a level of 0 to the sink nodes that have highest level values.
- 2. *Sort* button for applying selected sorting algorithm onto selected network and updating the network layout respectively.
- 3. Change network layout after sorting checkbox if checked, the network layout will be changed by arranging the nodes from left to right from lower to higher levels. Note that the original layout will not be preserved.
- 4. Calculate Significance after calculating flow checkbox if checked, significance values of PSF values for all the nodes will be computed by Bootstrap resampling. The node input values are reshuffled during each resampling, and the PSF values are computed again. After multiple resamplings, the obtained distribution of PSF values for each node is used to calculate the z-score and the p value (see PSFC algorithms for details). The p values will appear in the "psfc_pval" node attribute column.

- 5. Radio buttons specifying the mode of Bootstrap resampling.
 - a. Sample centric the values of the nodes in the network will be reshuffled among each other during resampling.
 - b. *Gene centric* the value of each node is randomly chosen from a supplied distribution of node values. Such a distribution, e.g., may come from microarray chips, where the expression of a single gene is measured in several samples.
- 6. *Exp Matrix* button (for *Gene centric* option)— select the file, where the value distributions of nodes are specified. This is a tab delimited file, where the first column contains the node names, and the tab delimited values of the node are written in each row.

Rules tab




The *Rules* tab contains the following components:

- Open Rule Presets Guide button opens the PDF file, where preset options for the Rules tab are
 explained. If the PDF doesn't open for some reason, you should open manually from the PSFC appdata directory specified in the task monitor.
- 2. Simple rules panel for setting edge type specific rules onto single edges. Defines how a signal is transferred from a source to a target node, via a single edge.
- 3. Choose EdgeTypes config file button sets the configuration file containing edge type rule name mapping. This should be a tab delimited file, where the first column contains edge types, and the second column contains the names of the functions assigned to each edge type.
- 4. Choose Rule config file button sets the configuration file containing function name function mapping. This should be a tab delimited file, where the first column contains the function names, and the second column contains the function specifications corresponding to each name. The

functions should be of the form *f*(*source*, *target*), where *source* is the source node signal, and *target* is the target node value.

- 5. Multiple input and output edge rules panel for setting rules to process signals from multiple edges starting from a single source node or ending on a single target node.
- 6. Signal split rule specifies whether to split multiple edges outgoing from a single source (or incoming to a single target node), (i) by dividing to the number of edges (Equal); (ii) by assigning weights to edges proportional to relative values of the target nodes (or relative signals of the source nodes) (Proportional); (iii) by assigning the edges user supplied weights (Supplied Weights); (iv) alternatively there can be no splitting at all (None).
 - 6a. The CyColumn in Default Edge table of the selected network, which contains edge weight attribute values; should be of Floating Point type; is active when *Supplied weights* option is selected.
 - *6b.* Refresh button for supplied weights column -updates the list of columns of the selected network's Default Edge Table; should be used when a column is added or removed from the table.
- Split signal on specifies which edges to apply splitting on: Incoming: multiple edges ending on a single target node; Outgoing – multiple edges starting from a single source node.
- 8. Multiple signal processing rule specifies how multiple signals received by a single node should be processed be added (Addition) or multiplied (Multiplication) and replace the previous node signal, or the signals should be processed one after another, each of them replacing the previous node signal (Updated node scores).
- 9. Signal processing order if the Multiple signal processing rule is set to Update node scores, the order in which the edges are processed matters. If set to None, the edges will be processed one after the other in random order; alternatively the user may supply Edge ranks, defining the relative priorities of the edges: the smaller the rank, the sooner the edge will be processed.
 - 8a. The CyColumn in Default Edge table of the selected network, which contains edge rank attribute values; should be of Floating Point type; is active when *Edge ranks* option is selected.
 - 8b. Refresh button for edge ranks column updates the list of columns of the selected network's Default Edge Table; should be used when a column is added or removed from the table.

Loops tab




The *Loops* tab specifies how to handle feedback loops in a pathway. It has the following three options:

- 1. Ignore feedback loops in the pathway checkbox if checked, the backward edges that form feedback loops will not be considered during PSF calculations.
- 2. Iterate until convergence checkbox if checked, the PSF calculations will consider loop forming backward edges as other edges in the pathway, and the algorithm will run for several rounds until reaching convergence. Convergence in reached if the relative percent difference between node signals in two consecutive iterations is less than the specified threshold (2a). If convergence is not reached, the computation will finish after the specified maximum number of iterations (2b).
- 3. Precompute signals at loops checkbox if checked, the signal at backward edges is firstly computed, and their target node values are updated. Afterwards, the PSF calculation is run on the whole network in *Ignore feedback loops* mode.

PSFC algorithms

Network sorting

For computation of pathway signal flow propagation, the network should initially be sorted based on distances of intermediate nodes from the input nodes, where input nodes, i.e. nodes that don't have incoming edges, should be assigned level 0. In order to see network sorting results before pathway flow calculation, the user may press the Sort button (4) in Network tab panel. PSFC will sort the selected network and optionally apply the level based layout onto network view. psfc.level column will appear in the default node table of the selected network, where the level of each node will be indicated.



Currently, only a modified version topological sort algorithm is provided as an option. For directed acyclic graphs (DAGs) topological sorting algorithm orders the vertices of a graph in a way that for every edge uv for nodes u and v, u comes before v in the ordering. The algorithm uses JGraphT's TopologicalOrderIterator, but considers the fact that the graph may have more than one input vertex. Biological pathways, however, mostly contain cycles that represent positive or negative feedback loops. For sorting cycle-containing graphs, we first remove backward edges, which are found with a modified depth-first search algorithm (which also accounts for multiple input nodes). After removing the backward edges, the resulting graph is sorted with topological sorting algorithm, and finally the backward edges are restored in the graph.

Flow propagation rules

In biological signaling networks, functional interaction types can be broadly defined as activation or inhibition, while the range of physical and regulatory interactions is much wider (phosphorylation, binding, dimerization, ubiquitination, etc). Because of different types of interactions, each edge in a pathway should be associated with a different function that will describe how signal will propagate from its source node to the target.

Rules for signal flow propagation for single edges are defined with two files.

- EdgeTypes config file should be a tab delimited file, where the first column indicates the edge types, and the second column indicates rule names corresponding to each edge type. All the edge types in the selected network should be present in the config file in order for PSF calculation to be performed.
- Rule config file should be a tab delimited file, where the first column indicates the rule names, and the second column indicates the functions corresponding to each rule name. All rule names corresponding to all the edge types in the selected network should be present in this file. Functions are defined as mathematical equations of the form f(source, target), with variables named "source" and "target" for source and target nodes respectively. The user defined edge-type functions are parsed with Exp4j Java library [] for symbolic operations. The parsable functions include a number of mathematical operations, including sin, cos, log (natural logarithm), and constants, such as Math.Pl, Math.E.

Rules for multiple incoming and outgoing signals are applied for the cases when multiple edges go out of a single source node (multiple outgoing edges), or multiple edges go to a single target node (multiple incoming edges).


Signal splitting: Generally, intensity of interactions between molecules largely depends on their concentration and activation state. However, if one type of molecule has several interacting partners, those may compete with each other, and the interaction capacity of the molecule may be "split" between those partners. Following this idea, PSFC is implemented with different options for splitting the signal among multiple outgoing or incoming edges.

The splitting of the signals is performed as follows:

(i) Edges are assigned weights according to the splitting rule. If the rule is set to "Equal", the weight of each edge is calculated by dividing 1 to the number of edges. If the rule is set to "Proportional", and

edges are split on edges outgoing from a single source node, each edge gets a weight equal to the relative signals of its target nodes. If edges ending at a single target are split with the "Proportional" rule, the relative source signals are used for weight assignment. Alternatively, the user may supply weights of their choice.

- (ii) The assigned edge weights are multiplied by the source node signal, if splitting is performed on multiple outgoing edges, or by the target node value, in case of splitting on multiple incoming edges;
- (iii) Finally, the edge-associated function is applied to the weighted source and target node signals.



Multiple signal processing: Multiple signals entering a single target node may be processed in one the following three ways: those may be processed separately and the resulting signals added to each other (i) or multiplied (ii), or those may be processed in sequence, by updating the signal at a target node, each time an edge is processed (iii). The order, in which the edges are processed in the last case may be adjusted by the user by defining rank-based edge order (see the User Manual for details).

Pathway flow calculation

Pathway flow calculation is the process of signal propagation from nodes at the first level to the nodes at the last level of the network. At each level assigns weights to the edges, according to the options set with

Signal split rule and Split signal on (button group no. 5 and 6 in the Rules tab). For each edge, the signal at the edge is computed based on the edge type-specific rule and the source and target node values, and multiplied by its weight. If a node has several incoming edges, the edge signals are processed and accumulated in the target node, according to Multiple signal processing rule and Signal processing order (button group no. 7 and 8 in the Rules tab).

To perform pathway flow calculation on the selected network, after setting the respective options simply press the *Calculate flow* button. Nodes and edge signals will be updated and the signals of all the nodes and edges will be visible in newly created or updated columns in default node and edge tables of the selected network in Cytoscape. The column names will have the suffix "psf_I" followed by the level value. Signal values are also kept in the score backup xls file, kept in the apps directory, usually located at C:\Users\User\CytoscapeConfiguration\app-data\PSFC\ (the address is indicated in TaskMonitor). The log of PSF calculation steps are debugged in PSFC log file, which is located in the apps directory, usually located at C:\Users\User\CytoscapeConfiguration\app-data\PSFC\PSFC.log, and can be opened by pressing the *PSFC log* button in the bottom of the panel.

Flow visualization

The *Flow visualization* panel allows the user to see the updated node signals by applying color based visual mapping of the values in the "psf_I" columns. The *Show state* button will show the node signals at the state when the flow propagation has reached the nodes of the level indicated on the levels' slider or level textbox. The *Play flow* button will sequentially visualize node signals at all the levels. In case of iterative loop handling, the pathway flow is visualized for the last iteration only.